

Description

This document tells you how to install a INTERMEC Printer PC4 or P4, or a DATAMAX Printer Alegro or M Class on a Windows XP professional, 2000 or 2003 server where Sprinter2000 is installed.

Installing the INTERMEC C4,PC4 Printer

The INTERMEC C4,PC4 should be installed with the Generic / Text Only Printer driver that comes standard with windows **and not with the software that came with the printer!!!**

To install the printer driver you will need Administrator rights on the server!

Go to:

Control panel > Printers and Faxes

And click on 'Add Printer' and follow the wizard;

1. choose 'Local Printer' and remove the tick at 'automatically detect' option.
2. choose the appropriate printer port.
3. choose in the left panel 'Generic' .
4. next in the right panel 'Generic/Text Only'.
5. 'Replace existing Driver'.
6. Printer name (leave as is, or name it whatever suits you).
7. If you have more than one pc using Sprinter2000 you should also share this printer on your network. Give the printer a name. *example: generic*
8. *if the next step asks to describe a location to the capabilities, skip it.*
9. Print a test page? (not necessary).
10. Finish!

As you will see, a printer is added in the overview window.

When this is done, go to Sprinter2000...

Click on **System > Document settings**

search for 'Road Cargo Labels'

Remove the tick at 'eject' if it is ticked.

Set all margins to "0".

change the printer name from DEFAULT to \\servername\generic or

\\ipnumber\generic and alter the other settings as you wish and if needed.

If this is done we have to tell Sprinter2000 that we are going to use the INTERMEC instead of the DEFAULT laser printer...

Follow these steps:

1. Go to: **System > Options**
2. Search for AIRLABELLJ
3. untick the Logic option.
4. Search for INTERMECC4
5. tick the Logic option.

Installing a DATAMAX Alegro or M Class Label Printer

The DATAMAX Alegro, M Class should be installed with the Generic / Text Only Printer driver that comes standard with windows **and not with the software that came with the printer!!!**

To install the printer driver you will need Administrator rights on the server!

Go to:

Control panel > Printers and Faxes

And click on 'Add Printer' and follow the wizard;

11. choose 'Local Printer' and remove the tick at 'automatically detect' option.
12. choose the appropriate printer port.
13. choose in the left panel 'Generic' .
14. next in the right panel 'Generic/Text Only'.
15. 'Replace existing Driver'.
16. Printer name (leave as is, or name it whatever suits you).
17. If you have more than one pc using Sprinter2000 you should also share this printer on your network. Give the printer a name. *example: generic*
18. *if the next step asks to describe a location to the capabilities, skip it.*
19. Print a test page? (not necessary).
20. Finish!

As you will see, a printer is added in the overview window.

When this is done, go to Sprinter2000...

Click on **System > Document settings**

search for 'Road Cargo Labels'

Remove the tick at 'eject' if it is ticked.

Set all margins to "0".

change the printer name from DEFAULT to \\servername\generic or

\\ipnumber\generic and alter the other settings as you wish and if needed.

If this is done we have to tell Sprinter2000 that we are going to use the DATAMAX instead of the DEFAULT laser printer...

Follow these steps:

6. Go to: **System > Options**
7. Search for AIRLABELLJ
8. untick the Logic option.
9. Search for INTERMECC4
10. untick the Logic option (if ticked).
11. Search for CITOHEZ4TT
12. untick the Logic option (if ticked).

More settings (for INTERMEC & DATAMAX)

If you want to print the following labels on the Labelprinter, you have to set the following settings:

General Road Label: search for ROALABELLJ and tick the Logic option

General Sea Label: search for SEALABELLJ and tick the Logic option

General Air Label: search for AIRLABELLJ and tick the Logic option

(INTERMEC ONLY)IATA Cargo Label: search for INTERMEVER and select one of the two label options in the field 'number':

1. IATA std. company name only
2. Tel nr, website and company name

Close the window and try it out with a Road shipment.